

# How to change location of the Sentinel USB Key

171 [Frank Mateo](#) Wed, Feb 16, 2011 [Time Guardian Pro 3.7 or lower](#) 0 7982

**AMANO.**

## Introduction

Amano recommends the following steps for how to change location of the sentinel USB key for Time Guardian (TG) Pro version 3.7 or lower and TG Plus version 1.

**Use the following steps;**

1. Move the Sentinel Key to the new computer.
2. Get the IP address of the new computer that you are moving the key to?
3. Install the Sentinel driver program on the new computer.
4. Go to the server where TG Pro is running.
5. Add an environment variable in the System Menu of Windows - Advanced Tab.
6. Choose System Variable (this will affect any profile logged in).
7. Under System Variable add the following information:
8. Variable Name = NSP\_HOSTS
9. Variable Value = 111.111.111.111 (IP address of the computer with the Sentinel Ley).
10. Once you are finished, restart the Setinel services and then open TG Pro or TG Plus.

---

## Conclusion

Thank you for your time, and have a great day. As always, feel free to submit ideas on topics you want addressed in the Amano Knowledge Base using the comments feature.

Amano Cincinnati, Inc. reserves the right to make equipment changes and improvements which may not be reflected in this article. Portions of this article may have been updated to include the latest hardware or firmware version, if applicable. Amano assumes no liability for errors and/or omissions. If you should find any errors or unclear information, please notify Amano by posting a comment.

<b>Customer Support Information</b>	Call toll-free in the U.S.: 800-253-9836 (outside U.S. call 973-364-0294) or Fax: 973-364-1091 Mailing address: Amano Cincinnati, Inc., 140 Harrison Ave., Roseland, New Jersey 07068 Web site: <a href="http://www.amano.com/time">www.amano.com/time</a> • E-mail: <a href="mailto:support@amano.com">support@amano.com</a>
---	---

Online URL: <http://tkb.amano.com/article.php?id=171>